



Limcet BOX upgrade

instructions I. **Software replication steps**,
prepare before upgrading:

1-1. Prepare a **USB** flash drive with less than 16G
memory; 1-2 **Format the USB flash drive as FAT32**
as shown in the figure below:



1-3. Copy the software to the **USB** flash drive as shown in the following figure:




11. Upgrade specification process:


2. Turn on the power supply of the vehicle and enter the installation interface. After the system is started, insert the USB flash drive, as shown in the figure below.

Operate in turn (please do not disconnect the car and unplug the USB flash drive during the upgrade process);


2-1. Enter the installation interface.




2-2 Insert the USB flash drive with the software, and the system will enter the following interface without any operation. After waiting for 5 seconds, the system will automatically update the configuration file.



2-3. Then wait for the system to enter the following interface (3 successes, 0 failures) ; click OK to restart the system, and the system will automatically enter the software upgrade. ,



2-4. The system will automatically enter the software upgrade. The interface prompt is shown in the figure below. This upgrade step will wait for about 90 seconds. Don't do anything until the system restarts.



2-5. Automatically restart after the system update is completed. Don't pull out the USB flash drive and wait for the system to upgrade configuration, as shown in the figure below.

如果出现自动重启以后 没有跳出配置文件升级，把U盘拔出重新插入即可



Note: First unplug the software USB flash drive and then select "OK" at this time, the system restarts and upgrades again. Complete

III. Enter the system settings and select the corresponding functional configuration according to the vehicle configuration, such as: reversing mode-related configuration, radar, trajectory, etc., language settings, voice button settings, front-view settings, right blind zone settings, etc.